



Language/Date/Time /Temperature Format Setup

Subject: Language/Date/Time/Temperature Format Setup

Date: January 29, 2026

Models / Parts Affected: TCIM

Voltages: All Voltages


Overview

This document describes how to set the language, date, time, and temperature format on TCIM models.


Procedures

Set the Language


1. Power the TCIM.
2. Press the menu gear icon.




3. Press the date and time icon.




4. Select the language menu.



5. Select the desired language. Press okay .



6. In the **Date, Hour, and Language** screen, the desired language appears. Return to the home screen. Press the back icon twice (2x).






Language/Date/Time /Temperature Format Setup


Procedures (cont.)

Set the Date Format and Date


1. Power the TCIM.
2. Press the menu gear icon.




3. Press the date and time icon from the menu screen.




4. Press the date format button to select the date format. True offers US and EU date formats.



5. Press the date button.




6. Press the year.



7. Enter the correct year and press okay.



8. Open the month drop down list and select the correct month.




Language/Date/Time /Temperature Format Setup


Procedures (cont.)

Set the Date Format and Date (cont.)

9. Select the correct date and press okay.



10. In the **Date, Hour, and Language** screen, the correct date appears in the screen's lower left corner. Return to the home screen; press the back icon twice (2x).






Language/Date/Time /Temperature Format Setup


Procedures (cont.)

Set the Time Format and Time


1. Power the TCIM.
2. Press the menu gear icon.




3. Press the date and time icon from the menu screen.




4. Press the time format button to select the time format. True offers 12 hour and 24 hour time formats.




5. Press the time button.



6. Press **CLR** to clear the current time shown.



7. Enter the correct hour and minutes. Then, if applicable, select **AM** or **PM**.






Language/Date/Time /Temperature Format Setup


Procedures (cont.)

Set the Time Format and Time (cont.)

8. Press okay.




9. In the **Date, Hour, and Language** screen, the correct time appears in the screen's lower right corner. Return to the home screen; press the back icon twice (2x).




Set the Temperature Format


1. Power the TCIM.
2. Press the menu gear icon.




3. Press the date and time icon from the menu screen.



4. Press the temperature format icon to select the temperature format. True offers Fahrenheit (°F) and Celsius (°C) temperature formats.



5. Return to the home screen; press the back icon twice (2x).





Language/Date/Time /Temperature Format Setup

Technical Questions or Concerns

For more information, please contact our Technical Support team.

Warranty Phone: +1 855-299-3510

Warranty Email: WarrantyInquiries@TrueMfg.com

Technical Phone: +1 888-783-1429

Technical Email: CommercialIce@TrueMfg.com